ERRATA

Creative Writer — Commodore 64 Version

Page 6

DELETING TEXT.

Add: To delete a blank line: Place the cursor on that blank line and press INST/DEL. The line will disappear.

INSERTING TEXT.

Add: To insert a blank line: If you have a blank line and want to add another blank line, place the cursor on the existing blank line and press INST/DEL while holding down the shift key.

Another way to insert a blank line is simply to place the cursor in the first position of a line of text and hit RETURN. A blank line will appear.

Page 11

PAGE FORMAT.

Sentence 4 should read: To change any of these values, move the cursor to the value you want to change and type over the displayed value shown under the heading Current Value and then press RETURN.

Page 14

CHAPTER THREE, Advanced Editing Commands.

Add to paragraph 3: To exit the COMMAND mode, press f 1 again while the COMMAND BANNER IS DISPLAYED.

Page 6

CURSOR MOVEMENT.

After paragraph 3, add: Cursor tabs (not to be confused with imbedded print tabs discussed on pages 23 and 24) are available in five-character increments, by pressing the RUN/STOP key. Simply press the RUN/STOP key and the cursor will move five spaces to the right.

Page 21

CHAPTER FOUR, Imbedded Print Controls.

After paragraph 3, add: For the CTRL l (left margin), CTRL r (right margin), CTRL s (spacing) and CTRL t (tab) commands, you must continue holding down the CTRL key as you type in the number following these imbedded commands. The number will also appear in reverse video.

LEFT AND RIGHT MARGINS.

The paragraph should read: To set the left margin, you hold the CTRL key down and type l (lower case L); a reverse "l" appears. Now type in the column number while continuing to hold down the CTRL key. To set the right margin, type CTRL r, followed by the numerical value for the new right margin (while continuing to hold down the CTRL key). Creative Writer won't let you make a mistake. If you try to set a right margin with a smaller number than you do for the left margin Creative Writer will not accept it. An error message will be displayed when the document is previewed or printed.

Page 22

JUSTIFICATION:

Sentence 4 should read: Then press CTRL b (for begin).

Sentence 7 should read: Type CTRL j, then type CTRL e (for end) justification.

ADDITIONAL FEATURES:

1. HELP LIBRARY. Press function key f 3. The HELP LIBRARY will appear. Move the cursor to the option you want and press RETURN. Additional information on that option will appear on the screen.
2. If you wish to eliminate the dots on the screen, hit the SHIFT and RUN/STOP keys simultaneously. Use the same procedure to return the dots to the screen.

NOTE: If you get a "disk error" message on the screen, you must remove and reinsert the disk in the disk drive before starting again.